

Firmware Revision Info:

DMC-40x0 Controller

New features for Rev 1.1d1 May 4, 2011:

- Modified BX Command Algorithm
- Added BX<n for BX pulse duration
- Added BI-1 for Galil Sine Amplifier Hall Commutation
- Added support for BC and BI with internal Sine Amplifiers

New features for Rev 1.1d April 8, 2011:

- Frequency Analysis Software support added
- AMP-43240, AMP-43540 and AMP-43640 support added

New features for Rev 1.0c October 7, 2009:

- Added PVT motion profiling mode
- WT and AT enhanced to allow waits of either samples or units of time

New features for Rev 1.0b February 18, 2009:

- Added SDM-44140 to ID command
- Added subroutine parameter passing
- Added EI command to generate UDP packets upon controller events
- Ethernet firmware download

New features for Rev 1.0a1 June 10, 2008 :

- No new features added

New features for Rev 1.0a February 6, 2008 :

- Added DT-1 to pause contour buffer execution
- Added stop code 16 for stepper position error

- Added DH command to support DHCP service
- Block IP ports<1000 except for 0,23,68 and 502 with IK command
- Added AF-1 for analog input sampling

New features for Rev 1.0 January 3, 2007 :

- Firmware Released